

CS3600 — SYSTEMS AND NETWORKS


NORTHEASTERN UNIVERSITY

Lecture 24: Congestion Control

Prof. Alan Mislove (amislove@ccs.neu.edu)

Slides used with permissions from Edward W. Knightly,
T. S. Eugene Ng, Ion Stoica, Hui Zhang

Abstract View




- We ignore internal structure of network and model it as having a single bottleneck link

Three Congestion Control Problems


- Adjusting to bottleneck bandwidth
- Adjusting to variations in bandwidth
- Sharing bandwidth between flows

Single Flow, Fixed Bandwidth



- Adjust rate to match bottleneck bandwidth
 - without any *a priori* knowledge
 - could be gigabit link, could be a modem

Single Flow, Varying Bandwidth




- Adjust rate to match instantaneous bandwidth
- Bottleneck can change because of a routing change

Multiple Flows

Two Issues:

- Adjust total sending rate to match bottleneck bandwidth
- Allocation of bandwidth between flows



General Approaches

- **Send without care**
 - many packet drops
 - could cause congestion collapse
- **Reservations**
 - pre-arrange bandwidth allocations
 - requires negotiation before sending packets
- **Pricing**
 - don't drop packets for the high-bidders
 - requires payment model

General Approaches (cont'd)

- Dynamic Adjustment (TCP)
 - Every sender probe network to test level of congestion
 - speed up when no congestion
 - slow down when congestion
 - suboptimal, messy dynamics, simple to implement

- Distributed coordination problem!

TCP Congestion Control


- TCP connection has window
 - controls number of unacknowledged packets
- Sending rate: $\sim \text{Window}/\text{RTT}$
- Vary window size to control sending rate
- Introduce a new parameter called congestion window (cwnd) at the sender
 - Congestion control is mainly a sender-side operation

Congestion Window (*cwnd*)

- Limits how much data can be in transit
- Implemented as # of bytes
- Described as # packets in this lecture

$\text{MaxWindow} = \min(\text{cwnd}, \text{AdvertisedWindow})$

$\text{EffectiveWindow} = \text{MaxWindow} - (\text{LastByteSent} - \text{LastByteAcked})$



Two Basic Components

- Detecting congestion
- Rate adjustment algorithm (change cwnd size)
 - depends on congestion or not

Detecting Congestion

Detecting Congestion

- Packet dropping is best sign of congestion
 - delay-based methods are hard and risky
- How do you detect packet drops? ACKs
 - TCP uses ACKs to signal receipt of data
 - ACK denotes last contiguous byte received
 - actually, ACKs indicate next segment expected
- Two signs of packet drops
 - No ACK after certain time interval: time-out
 - Several duplicate ACKs (ignore for now)

Detecting Congestion





- Packet dropping is best sign of congestion
 - delay-based methods are hard and risky
- How do you detect packet drops? ACKs
 - TCP uses ACKs to signal receipt of data
 - ACK denotes last contiguous byte received
 - actually, ACKs indicate next segment expected
- Two signs of packet drops
 - No ACK after certain time interval: time-out
 - Several duplicate ACKs (ignore for now)

Detecting Congestion

- Packet dropping is best sign of congestion
 - delay-based methods are hard and risky
- How do you detect packet drops? ACKs
 - TCP uses ACKs to signal receipt of data
 - ACK denotes last contiguous byte received
 - actually, ACKs indicate next segment expected
- Two signs of packet drops
 - No ACK after certain time interval: time-out
 - Several duplicate ACKs (ignore for now)
- May not work well for wireless networks, why?


Sliding (Congestion) Window

- Sliding window: each ACK = permission to send a new packet
 - Ex. cwnd = 3



Self-clocking


- If we have a large window, ACKs “self-clock” the data to the rate of the bottleneck link
- Observe: received ACK spacing \cong bottleneck bandwidth




Rate Adjustment

- **Basic structure:**
 - Upon receipt of ACK (of new data): increase rate
 - Data successfully delivered, perhaps can send faster
 - Upon detection of loss: decrease rate
- **But what increase/decrease functions should we use?**
 - Depends on what problem we are solving

Fairness?




Fairness?



Fairness?


Two competing sessions:



Fairness?

Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases



Fairness?

Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases
- multiplicative decrease (MD) decreases throughput proportionally



Fairness?

Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases
- multiplicative decrease (MD) decreases throughput proportionally



Fairness?

Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases
- multiplicative decrease (MD) decreases throughput proportionally



Fairness?

Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases
- multiplicative decrease (MD) decreases throughput proportionally



Fairness?

Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases
- multiplicative decrease (MD) decreases throughput proportionally





Fairness?


Two competing sessions:


- Additive increase (AI) gives slope of 1, as throughput increases
- multiplicative decrease (MD) decreases throughput proportionally





















































AIMD Sharing Dynamics







- No congestion \rightarrow rate increases by one packet/RTT every RTT
- Congestion \rightarrow decrease rate by factor 2





















AIAD Sharing Dynamics



- No congestion \rightarrow x increases by one packet/RTT every RTT
- Congestion \rightarrow decrease x by 1



Adapting cwin

- So far: sliding window + self-clocking of ACKs
- How to know the best cwnd (and best transmission rate)?
- Phases of TCP congestion control
 1. Slow start (getting to equilibrium)
 1. Want to find this very very fast and not waste time
 2. Congestion Avoidance
 - Additive increase - gradually probing for additional bandwidth
 - Multiplicative decrease - decreasing cwnd upon loss/timeout

Phases of Congestion Control

- **Congestion Window (`cwnd`)**
Initial value is 1 MSS (=maximum segment size) counted as bytes
- **Slow-start threshold Value (`ss_thresh`)**
Initial value is the advertised window size
- **slow start** ($cwnd < ssthresh$)
- **congestion avoidance** ($cwnd \geq ssthresh$)

TCP: Slow Start

- Goal: discover roughly the proper sending rate quickly
- Whenever starting traffic on a new connection, or whenever increasing traffic after congestion was experienced:
 - Initialize *cwnd* = 1
 - Each time a segment is acknowledged, increment *cwnd* by one (*cwnd*++).
- Continue until
 - Reach *ss_thresh*
 - Packet loss


Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!




Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!



Slow Start Illustration

- The congestion window size grows very rapidly
- TCP slows down the increase of *cwnd* when ***cwnd* \geq *ss_thresh***
- Observe:
 - Each ACK generates two packets
 - slow start increases rate exponentially fast (doubled every RTT)!



Congestion Avoidance (After Slow Start)



- Slow Start figures out roughly the rate at which the network starts getting congested
- Congestion Avoidance continues to react to network condition
 - Probes for more bandwidth, increase cwnd if more bandwidth available
 - If congestion detected, aggressive cut back cwnd

Congestion Avoidance: Additive Increase

- After exiting slow start, slowly increase *cwnd* to probe for additional available bandwidth
 - Competing flows may end transmission
 - May have been “unlucky” with an early drop
- **If *cwnd* > *ss_thresh* then**
each time a segment is acknowledged
increment *cwnd* by $1/cwnd$ ($cwnd += 1/cwnd$).
- *cwnd* is increased by one only if all segments have been acknowledged
 - Increases by 1 per RTT, vs. doubling per RTT

Example of Slow Start + Congestion Avoidance

Assume that *ss_thresh* = 8




Detecting Congestion via Timeout

- If there is a packet loss, the ACK for that packet will not be received
- The packet will eventually timeout
 - No ack is seen as a sign of congestion

Congestion Avoidance: Multiplicative Decrease

- Timeout = congestion
- Each time when congestion occurs,
 - ss_thresh is set to half the current size of the congestion window:
$$ss_thresh = cwnd / 2$$
 - cwnd is reset to one:
$$cwnd = 1$$
 - and slow-start is entered

TCP illustration



Responses to Congestion (Loss)


- There are algorithms developed for TCP to respond to congestion
 - **TCP Tahoe** - the basic algorithm (discussed previously)
 - **TCP Reno** - Tahoe + fast retransmit & fast recovery
 - Most end hosts today implement TCP Reno
- and many more:
 - TCP Vegas (research: use timing of ACKs to avoid loss)
 - TCP SACK (future deployment: selective ACK)

TCP Reno

- Problem with Tahoe: If a segment is lost, there is a long wait until timeout
- Reno adds a **fast retransmit** and **fast recovery mechanism**
- Upon receiving 3 duplicate ACKs, retransmit the presumed lost segment (“fast retransmit”)
- But do not enter slow-start. Instead enter congestion avoidance (“fast recovery”)

Fast Retransmit


- Resend a segment after 3 duplicate ACKs
 - remember a duplicate ACK means that an out-of-sequence segment was received
 - ACK-n means packets 1, ..., n **all** received
- Notes:
 - duplicate ACKs due to packet reordering!
 - if window is small don't get duplicate ACKs!



Fast Recovery

- After a **fast-retransmit**
 - $cwnd = cwnd/2$ (vs. 1 in Tahoe)
 - $ss_thresh = cwnd$
 - i.e. starts congestion avoidance at new $cwnd$
 - Not slow start from $cwnd = 1$
- After a **timeout**
 - $ss_thresh = cwnd/2$
 - $cwnd = 1$
 - Do slow start
 - Same as Tahoe

Fast Retransmit and Fast Recovery



- Retransmit after 3 duplicate ACKs
 - prevent expensive timeouts
- Slow start only once per session (if no timeouts)
- In steady state, *cwnd* oscillates around the ideal window size.

TCP Congestion Control Summary

- Measure available bandwidth
 - slow start: fast, hard on network
 - AIMD: slow, gentle on network
- Detecting congestion
 - timeout based on RTT
 - robust, causes low throughput
 - Fast Retransmit: avoids timeouts when few packets lost
 - can be fooled, maintains high throughput
- Recovering from loss
 - Fast recovery: don't set cwnd=1 with fast retransmits

TCP Reno Quick Review

- **Slow-Start** if $cwnd < ss_thresh$
 - $cwnd++$ upon every new ACK (exponential growth)
 - Timeout: $ss_thresh = cwnd/2$ and $cwnd = 1$
- **Congestion avoidance** if $cwnd \geq ss_thresh$
 - Additive Increase Multiplicative Decrease (AIMD)
 - ACK: $cwnd = cwnd + 1/cwnd$
 - Timeout: $ss_thresh = cwnd/2$ and $cwnd = 1$
- **Fast Retransmit & Recovery**
 - 3 duplicate ACKS (interpret as packet loss)
 - Retransmit lost packet
 - $cwnd = cwnd/2$, $ss_thresh = cwnd$

TCP Reno Saw Tooth Behavior

